



DataCore vFilO

Command Line Reference

Version 4.2

About This Guide	10
Share Management.....	11
share-clone-create.....	11
share-create.....	11
share-delete.....	11
share-list.....	12
share-mount	12
share-move	13
share-objective-add	13
share-objective-list	13
share-objective-remove	13
share-offline.....	14
share-online	14
share-snapshot-create	14
share-snapshot-delete	14
share-snapshot-list.....	15
share-snapshot-restore.....	15
share-snapshot-schedule-list	15
share-snapshot-update	15
share-undelete.....	16
share-unmount	16
share-update.....	16
Windows	17
ad-discover.....	17
ad-join	17

ad-leave.....	17
ad-view.....	17
domain-idmap-add	17
domain-idmap-delete	18
domain-idmap-list.....	18
domain-idmap-reload.....	18
smb-config	18
System	19
backup-create	19
backup-restore.....	19
backup-schedule-list	19
backup-update	19
cluster-update.....	19
cluster-view.....	20
dns-list.....	20
dns-update.....	20
dp-update	20
event-list	21
event-smtpgw-define.....	21
event-smtpgw-list	21
ha-node-add.....	21
ha-node-decommission	22
heartbeat-send	22
heartbeat-update.....	22
heartbeat-view.....	22

ldap-clear	22
ldap-list	22
ldap-update.....	23
license-activate	23
license-deactivate	23
license-request-export.....	23
metric-list.....	23
nis-config.....	24
nis-view	24
notification-rule-create.....	24
notification-rule-list	24
notification-rule-remove.....	25
notification-rule-update	25
ntp-list.....	25
ntp-update	25
support-bundle	25
remote-site-add	26
remote-site-list	26
remote-site-remove.....	26
proxy-clear	26
proxy-set	27
schedule-create	27
schedule-delete	27
schedule-list.....	27
schedule-update	28

snmp-clear	28
snmp-config	28
snmp-disable	29
snmp-enable	29
snmp-view	29
software-apply	29
software-list	29
software-package-delete	30
software-update-cancel	30
software-update-status	30
software-upload	30
syslog-clear	30
syslog-config	30
syslog-disable	31
syslog-enable	31
syslog-view	31
system-shutdown	31
system-view	31
task-list	32
task-purge	32
task-resume	32
User and Group Management	33
builtin-group-user-add	33
builtin-group-user-list	33
builtin-group-user-remove	33

login-policy-update	33
login-policy-view	34
role-create	34
role-delete	34
role-list	34
role-update	35
user-create	35
user-delete	35
user-import	36
user-list	36
user-password-update	36
user-update	36
Data Management and Objectives.....	38
basic-objective-create	38
basic-objective-delete	38
basic-objective-list	39
basic-objective-update	39
condition-create	40
condition-delete	40
condition-list	40
condition-update	40
smart-objective-create	41
smart-objective-delete	41
smart-objective-export	41
smart-objective-import	41

smart-objective-list	42
smart-objective-update	42
Storage and Volumes	43
drive-list	43
logical-volume-create	43
logical-volume-delete	43
logical-volume-discover	43
logical-volume-list	43
node-add	44
node-list	44
node-mode-change	44
node-refresh	45
node-remove	45
node-storage-repair	45
node-update	45
object-storage-add	46
object-storage-update	46
object-volume-add	47
object-volume-decommission	47
object-volume-decommission-cancel	48
object-volume-fail	48
object-volume-list	48
object-volume-remove	48
object-volume-set-available	49
object-volume-set-unavailable	49

object-volume-update	49
volume-add	50
volume-assimilation	51
volume-decommission	51
volume-decommission-cancel	52
volume-fail	52
volume-group-create	52
volume-group-delete	52
volume-group-list	53
volume-group-update	53
volume-list	53
volume-remove	53
volume-update	54
Snapshots and Cloning	55
file-snapshot-create	55
file-snapshot-delete	55
file-snapshot-list	55
file-snapshot-restore	55
file-snapshot-schedule-list	56
file-snapshot-update	56
snapshot-retention-create	56
snapshot-retention-delete	56
snapshot-retention-list	56
snapshot-retention-update	57
Networking	58

floating-ip-add	58
floating-ip-remove	58
gateway-update	58
gateway-view	58
interface-create	58
interface-delete	59
interface-list	59
interface-update	59
static-route-add	60
static-route-delete	60
static-route-list	60
subnet-gateway-add	60
subnet-gateway-delete	60
subnet-gateway-list	60
Technology Preview	62
local-site-update	62
local-site-view	62
Alphabetical Command Index.....	63



About This Guide

This is the command line reference for DataCore vFilO.

The chapters reference different management areas and at the end is an alphabetical command index.

Share Management

share-clone-create

Usage: share-clone-create [options]

Clone share snapshot

Options:

- async Determines that the command will be executed asynchronously. A reference task identifier will be returned
- * --destination-path Destination directory path for clone. The path must be relative to the share's root directory
- help Display this help and exit
- overwrite-destination Whether to overwrite the destination directory if it exists
- * --share-id Share ID. Required unless "--share-name" is specified
- * --share-name Share name. Required unless "--share-id" is specified
- * --snapshot-name Name of snapshot to be cloned

share-create

Usage: share-create [options]

Create a share

Example: share-create --name share2 --path /share2 --export-option *,rw,no-root-squash

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- description A textual description of the share
- export-option Export options for the share. Each value must contain <subnet,access-permission,{no-}root-squash>.
- help Display this help and exit
- * --name The method the system uses to identify the share. This name should be unique between all shares.
- * --path The share path (i.e. /share1). The / prefix must be specified.
- preferred-domain Preferred domain in which users have accounts. This field is required for mapping users from another domain into this domain
- size Limit the share size (quota)
- size-warning-threshold Threshold (1-99 percent) for share capacity usage, an event will be sent if this threshold is reached.
- unmapped-group Default group name, if there is no mapping discovered into the preferred domain.
- unmapped-user Default user name, if there is no mapping discovered into the preferred domain.

share-delete

Usage: share-delete [options]

Delete a share

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- delay Postpone share space reclaim for period of time (for example 24h). Mutually exclusive with "-now"
- delete-path Delete the share path directory when the share is purged. Directory must be empty in order to be deleted
- help Display this help and exit
- * --id The ID of the share to delete. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the share to delete. Required unless "--id" or "--name" is specified
- * --name The name of the share to delete. Required unless "--id" or "--internal-id" is specified

--now Share space will be reclaimed immediately. Mutually exclusive with "--delay"

share-list

Usage: share-list [options]

Display a list of all shares available in the system. Two types of lists can be displayed: a full list and a summary list (default)

Options:

- full Print extra information
- help Display this help and exit
- id The ID of the share to list
- internal-id The internal ID of the share to list
- name The name of the share to list

share-mount

Usage: share-mount [options]

Mount a share

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- help Display this help and exit
- * --id The ID of the share to mount. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the share to mount. Required unless "--id" or "--name" is specified
- * --name A name to identify the share. Required unless "--id" is specified

share-move

Usage: share-move [options]
Move share to a different path

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- help Display this help and exit
- * --id The ID of the share to move. Required unless "--name" or "--internal-id" is specified
- * --name The name of the share to move. Required unless "--id" or "--internal-id" is specified
- * --internal-id The internal ID of the share to move. Required unless "--id" or "--name" is specified
- * --path Path to mount the share on (i.e. /share1). The / prefix must be specified.

share-objective-add

Usage: share-objective-add [options]
Apply an objective to a share (or at a path within the share)

Options:

- clear-existing Causes all previously added objectives at path to be removed
- help Display this help and exit
- * --id The ID of the share. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the share. Required unless "--id" or "--name" is specified
- * --name The name of the share. Required unless "--id" or "--internal-id" is specified
- * --objective The objective name
- path A path within the share to apply the objective to. When omitted, "/" is implied

share-objective-list

Usage: share-objective-list [options]
List the applied and active objectives for a share (or at a path within the share)

Options:

- help Display this help and exit
- * --id The ID of the share. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the share. Required unless "--id" or "--name" is specified
- * --name The name of the share. Required unless "--id" or "--internal-id" is specified
- path A path within the share to list the objectives for. When omitted, "/" is implied

share-objective-remove

Remove an applied objective from a share (or from a path within the share)

Options:

- help Display this help and exit
- * --id The ID of the share. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the share. Required unless "--id" or "--name" is specified
- * --name The name of the share. Required unless "--id" or "--internal-id" is specified
- objective The objective name to be removed. When omitted, all objectives applied locally are removed
- path A path within the share to remove the objective from. When omitted, "/" is implied

share-offline

Usage: share-offline [options]
Take a share to the offline state

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- help Display this help and exit
- * --id The ID of the share to take offline. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the share to take offline. Required unless "--id" or "--name" is specified
- * --name T The name of the share to take offline. Required unless "--id" or "--internal-id" is specified

share-online

Usage: share-online [options]
Bring a share to the online state

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- help Display this help and exit
- * --id The ID of the share to bring online. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the share to bring online. Required unless "--id" or "--name" is specified
- * --name The name of the share to bring online. Required unless "--id" or "--internal-id" is specified

share-snapshot-create

Usage: share-snapshot-create [options]
Create share snapshot
Example: share-snapshot-create --share-name test --now

Options:

- help Display this help and exit
- now Create immediate snapshot of the share
- retention-name Name to identify the retention
- schedule-name Name for the schedule of periodic snapshots of the share
- * --share-id Share ID. Required unless "--share-name" is specified
- * --share-name Share name. Required unless "--share-id" is specified

share-snapshot-delete

Usage: share-snapshot-delete [options]
Delete share snapshot

Options:

- help Display this help and exit
- * --share-id Share ID. Required unless "--share-name" is specified
- * --share-name Share name. Required unless "--share-id" is specified
- * --snapshot-name Snapshot name. May include wild-card characters (for example 2001-01-01T12-00*)

share-snapshot-list

Usage: share-snapshot-list [options]

List snapshots for share

Options:

- help Display this help and exit
- * --share-id Share ID. Required unless "--share-name" is specified
- * --share-name Share name. Required unless "--share-id" is specified

share-snapshot-restore

Usage: share-snapshot-restore [options]

Restore files from a share snapshot (when used with --filename option) or a complete share snapshot.

Options:

- async Determines that the command will be executed asynchronously. A reference task identifier will be returned. This option can be used only when restoring the entire share
- filename Paths for files to be restored from the share snapshot. Multiple paths may be provided. A path must be relative to the share root directory. The filename in the path may include wild-card characters (for example, /dir/file*.txt)
- help Display this help and exit
- * --share-id Share ID. Required unless "--share-name" is specified
- * --share-name Share name. Required unless "--share-id" is specified
- * --snapshot-name Share snapshot name

share-snapshot-schedule-list

Usage: share-snapshot-schedule-list [options]

List scheduled snapshots for share

Options:

- help Display this help and exit
- share-id Share ID
- share-name Share name

share-snapshot-update

Usage: share-snapshot-update [options]

Update share snapshot schedule

Options:

- clear-snapshots Delete all snapshots taken for the schedule. Can be provided along with remove-schedule
- help Display this help and exit
- new-retention-name Name to identify the retention
- remove-retention Remove retention from share snapshot schedule
- remove-schedule Remove both schedule and retention from share snapshot
- * --schedule-name Name for the schedule of periodic snapshots of the share
- * --share-id Share ID. Required unless "--share-name" is specified
- * --share-name Share name. Required unless "--share-id" is specified

share-undelete

Usage: share-undelete [options]
 Abort scheduled deletion a share

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- help Display this help and exit
- * --id A ID to identify the share. Required unless "--name" is specified
- * --name A name to identify the share. Required unless "--id" is specified

share-unmount

Usage: share-unmount [options]
 Unmount a share

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- help Display this help and exit
- * --id A ID to identify the share. Required unless "--name" is specified
- * --name A name to identify the share. Required unless "--id" is specified

share-update

Usage: share-update [options]
 Update a share

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- description A textual description of the share
- description-clear ""
- export-option Export options for the share. Each value must contain <subnet,access-permission,{no-}root-squash>
- export-option-clear ""
- help Display this help and exit
- * --id The ID of the share to update. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the share to update. Required unless "--id" or "--name" is specified
- * --name The name of the share to update. Required unless "-id" or "--internal-id" is specified
- preferred-domain Preferred domain in which users have accounts. This field is required for mapping users from another domain into this domain
- preferred-domain-clear Clear preferred domain attribute
- size Limit the share size (quota).
- size-clear Set no size limit on the share (no quota).
- size-warning-threshold Threshold (1-99 percent) for share capacity usage, an event will be sent if this threshold is reached.
- unmapped-group Default group name, if there is no mapping discovered into the preferred domain
- unmapped-group-clear Clear unmapped group attribute
- unmapped-user Default user name, if there is no mapping discovered into the preferred domain
- unmapped-user-clear Clear unmapped user attribute

Windows

ad-discover

Usage: ad-discover [options]
Discover active directory realm

Options:

- help Display this help and exit
- * --realm Active directory realm name

ad-join

Usage: ad-join [options]
Join active directory

Options:

- computer-ou The distinguished name of an organizational unit in which to create the computer account
- help Display this help and exit
- * --password Password
- * --realm Active directory realm
- * --username Username

ad-leave

Usage: ad-leave [options]
Leave from active directory

Options:

- help Display this help and exit

ad-view

Usage: ad-view [options]
View active directory configuration

Options:

- help Display this help and exit

domain-idmap-add

Usage: domain-idmap-add [options]
Create domain ID mapping rule

Options:

- * --attribute Rule attribute
- bidirectional Create bidirectional rule
- * --from Domain to map from
- help Display this help and exit
- inherit-from Inherit by subtrees of domain to map from

```
--inherit-to    Inherit by subtrees of domain to map to
--no-inherit-from  Don't Inherit by subtrees of domain to map from
--no-inherit-to  Don't Inherit by subtrees of domain to map to
--order        Rule order
* --to         Domain to map to
```

domain-idmap-delete

Usage: domain-idmap-delete [options]
Delete domain ID mapping rule

Options:

```
--from  Domain to map from
--help   Display this help and exit
--id    Domain mapping ID
--to    Domain to map to
```

domain-idmap-list

Usage: domain-idmap-list [options]
List domain ID mapping rules

Options:

```
--full  Print extra information
--help   Display this help and exit
--id    domain ID mapping ID
```

domain-idmap-reload

Usage: domain-idmap-reload [options]
Reload domain ID mapping rules

Options:

```
--help   Display this help and exit
```

smb-config

Usage: smb-config [options]
Configure SMB parameters

Options:

```
--help       Display this help and exit
--min-smb-client  The minimal SMB client protocol (SMB1, SMB2, SMB2_10, SMB3,
                  SMB3_11);
```

System

backup-create

Usage: backup-create [options]
Backup product configuration and metadata

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- help Display this help and exit
- * --ip IP address of the storage node
- now Create an immediate product backup
- * --path The NFS export path to the backup volume
- schedule-name Name for the periodic product backup schedule

backup-restore

Usage: backup-restore [options]
Restore product configuration and metadata backup

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- help Display this help and exit
- * --ip IP address of the storage node
- * --path The NFS export path to the backup volume

backup-schedule-list

Usage: backup-schedule-list [options]
List the product's backup schedule

Options:

- help Display this help and exit

backup-update

Usage: backup-update [options]
Update the product's backup schedule

Options:

- help Display this help and exit
- * --ip IP address of the storage node
- * --path The NFS export path to the backup volume
- remove-schedule Remove a schedule
- schedule-name Name for the periodic product backup schedule

cluster-update

Usage: cluster-update [options]

Update Cluster configuration

Options:

- help Display this help and exit
- online-activation-support Determines whether online license activation is allowed. Allowed values:[YES, NO]
- timezone Specifies the timezone
- vvol-support Determines whether the system supports VVOLs. Allowed values:[YES, NO]

cluster-view

Usage: cluster-view [options]
View the cluster configuration

Options:

- help Display this help and exit

dns-list

Usage: dns-list [options]
List the DNS configuration

Options:

- help Display this help and exit

dns-update

Usage: dns-update [options]
Update the DNS configuration

Options:

- help Display this help and exit
- servers Set DNS server(s)
- servers-clear Clear DNS servers

dp-update

Usage: dp-update [options]
Update data portal

Options:

- data-portal-id The data portal UUID
- data-portal-type The data portal type (NFS or SMB)
- disable Set the data portal admin state to DOWN
- enable Set the data portal admin state to UP
- help Display this help and exit
- node-name The node name

event-list

Usage: event-list [options]

List events generated by the system

Options:

- cleared Include only cleared events
- from-date List events after "from-date", in the format [yyyy-MM-dd|dd-MMM-yyyy]
[HH:mm:ss]
- full Print extra information
- help Display this help and exit
- id The ID of the event to list
- last-emitted List last emitted events
- severity List all events with severity greater than the given severity. Possible values:
DEBUG | INFORMATIONAL | NOTICE | WARNING | ERROR |
CRITICAL | ALERT | EMERGENCY.
- type List all events of a given type. e.g., SHARE_CREATED
- uncleared Include only uncleared events
- until-date List events before "until-date", in the format [yyyy-MM-dd|dd-MMM-yyyy]
[HH:mm:ss]

event-smtpgw-define

Usage: event-smtpgw-define [options]

Add an SMTP gateway which will be used for events and call home through a mail server

Options:

- from-address Source email address from which the events will be sent
- help Display this help and exit
- host SMTP host
- no-ssl Disable SSL secured connection
- password SMTP password
- port SMTP port
- ssl Enable SSL secured connection
- username SMTP username

event-smtpgw-list

Usage: event-smtpgw-list [options]

View SMTP configuration

Options:

- help Display this help and exit

ha-node-add

Usage: ha-node-add [options]

HA node add

Options:

- help Display this help and exit
- * --ip HA node IP address to be added

ha-node-decommission

Usage: ha-node-decommission [options]
HA node decommission

Options:

- help Display this help and exit
- * --id HA node ID to be decommissioned. Required unless "--name" is specified
- * --name HA node name to be decommissioned. Required unless "--id" is specified

heartbeat-send

Usage: heartbeat-send [options]
Sends a heartbeat log to support

Options:

- help Display this help and exit

heartbeat-update

Usage: heartbeat-update [options]
Update the heartbeat configuration

Options:

- disable Disables periodic heartbeat sending
- enable Enables periodic heartbeat sending
- help Display this help and exit
- interval Periodic heartbeat sending interval

heartbeat-view

Usage: heartbeat-view [options]
View the heartbeat configuration

Options:

- help Display this help and exit

ldap-clear

Usage: ldap-clear [options]
Clear the LDAP configuration

Options:

- help Display this help and exit

ldap-list

Usage: ldap-list [options]
List the LDAP configuration

Options:

--help Display this help and exit

ldap-update

Usage: ldap-update [options]

Update the LDAP configuration

Options:

* --base LDAP base DN

--help Display this help and exit

* --url LDAP base URL (example ldap://host:port)

license-activate

Usage: license-activate [options]

Activate license

Options:

--activation-file-uri Activation file URI. For example: file:/tmp/license.bin

* --activation-id License activation ID

--help Display this help and exit

license-deactivate

Usage: license-deactivate [options]

De-activate license

Options:

--help Display this help and exit

license-request-export

Usage: license-request-export [options]

Export request to activate license

Options:

* --activation-id License activation ID

* --export-uri Destination URI for license activation request. For example: file:/tmp/activation-request.bin

--help Display this help and exit

metric-list

Usage: metric-list [options]

List metrics

Options:

* --field Field names in the format: <table-name>.<column-name> (e.g., network.bytesSent)

--from-date Shows metrics after date "from-date" (default: now - 1h)

```
--func      Computational aggregate function. Possible values: MIN | MAX | MEAN | MEDIAN.  
--group-by   Time grouping interval. For example, 60s (seconds), 60m (minutes), 24h (hours),  
              7d (days), 52w (weeks)  
--help       Display this help and exit  
--limit      Total number of samples per column (default: 1000)  
--name       Name criteria on the metrics  
--object-type Object type criteria on the metrics  
--until-date Shows metrics before date "until-date"  
--uuid       Shows metrics on an object with the specified UUID
```

nis-config

Usage: nis-config [options]
Configure NIS servers

Options:

```
--disable    disable NIS service  
--enable    enable NIS service  
--help      Display this help and exit  
--servers   NIS servers configuration in the form domain:server, example: --servers  
              somedomain.local:192.168.3.17. This parameter may be repeated.  
--servers-clear Clear NIS servers
```

nis-view

Usage: nis-view [options]
View NIS configuration

Options:

```
--help      Display this help and exit
```

notification-rule-create

Usage: notification-rule-create [options]
Create a notification rule

Options:

```
* --format   Notification format Possible values: XML | DEBUG.  
  --help     Display this help and exit  
* --name    Rule name  
* --threshold Severity threshold Possible values: DEBUG | INFORMATIONAL | NOTICE |  
                  WARNING | ERROR | CRITICAL | ALERT | EMERGENCY.  
  --users    Destination users (each must have an email address)
```

notification-rule-list

Usage: notification-rule-list [options]
List notification rules

Options:

```
--full     Print extra information
```

--help Display this help and exit
--id Notification rule identifier
--name Notification rule name

notification-rule-remove

Usage: notification-rule-remove [options]
Remove a notification rule

Options:

--help Display this help and exit
* --id Notification rule identifier. Required unless "--name" is specified
* --name Notification rule name. Required unless "--id" is specified

notification-rule-update

Usage: notification-rule-update [options]
Update a notification rule

Options:

--help Display this help and exit
* --id Notification rule identifier. Required unless "--name" is specified
* --name Notification rule name. Required unless "--id" is specified
--new-format New notification format Possible values: XML | DEBUG.
--new-name New name
--new-threshold New severity threshold Possible values: DEBUG | INFORMATIONAL |
NOTICE | WARNING | ERROR | CRITICAL | ALERT |
EMERGENCY.

ntp-list

Usage: ntp-list [options]
List the NTP configuration

Options:

--help Display this help and exit

ntp-update

Usage: ntp-update [options]
Update the NTP configuration

Options:

--help Display this help and exit
--servers Set NTP sync server(s)
--servers-clear Clear NTP sync servers

support-bundle

Usage: support-bundle [options]
Collect logs and information from all nodes

Options:

- all Collect from all available nodes
- current Collect from current node (default)
- dest Save output file into a specific folder
- help Display this help and exit
- local Collect locally
- node Collect from specific node
- push Collect and push to Support Center

remote-site-add

Usage: remote-site-add [options]

Add a remote site

Options:

- * --address The remote site's IP address having a MGMT role
- help Display this help and exit

remote-site-list

Usage: remote-site-list [options]

List known remote sites

Options:

- full Print extra information
- help Display this help and exit
- id The ID of the site to be listed
- internal-id The internal ID of the site to be listed
- name The name of the site to be listed

remote-site-remove

Usage: remote-site-remove [options]

Remove a remote site

Options:

- help Display this help and exit
- * --id The ID of the site to be removed. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the site to be removed. Required unless "--id" or "--name" is specified
- * --name The name of the site to be removed. Required unless "--id" or "--internal-id" is specified

proxy-clear

Usage: proxy-clear [options]

Clear the proxy configuration for the support-bundle and heartbeat

Options:

- help Display this help and exit

proxy-set

Usage: proxy-set [options]

Configure the support-bundle and heartbeat sender to use proxy

Options:

--help Display this help and exit

--proxy-url The proxy URL to be used for support-bundle push and heartbeats (in the form http://a.b.c.d:pp)

schedule-create

Usage: schedule-create [options]

Create a schedule

Expression values follow cron syntax where:

' ' Commas separate lists

'-' Hyphens define ranges

'*' Wildcard matches all cases

'/' Slashes define step values i.e. */5 = every 5 minutes

Example: To create a schedule at 1:30 AM, 12:30 PM and 6:30 PM, Monday-Friday

schedule-create --name schedule_name --minute 30 --hour 1,12,18 --day-of-week MON-FRI

Options:

--day-of-month The day of month for schedule. Allowed values are: 1-31,-*/ (default value: *)

--day-of-week The day of week for schedule. Allowed values are: 1-7,SUN-SAT,-*/ (default value: *)

--help Display this help and exit

--hour The hour for schedule. Allowed values are: 0-23,-*/ (default value: *)

--minute The minute for schedule. Allowed values are: 0-59,-*/ (default value: *)

--month The month for schedule. Allowed values are: 1-12,-*/ (default value: *)

* --name The name of the schedule

schedule-delete

Usage: schedule-delete [options]

Delete a schedule

Options:

--help Display this help and exit

* --id The ID of the schedule to delete. Required unless "--name" is specified

* --name The name of the schedule to delete. Required unless "--id" is specified

schedule-list

Usage: schedule-list [options]

List schedules

Options:

--full Print extra information

--help Display this help and exit
 --id The ID of the schedule to list
 --name The name of the schedule to list

schedule-update

Usage: schedule-update [options]

Update a schedule

Expression values follow cron syntax where:

- ' ' Commas separate lists
- '-' Hyphens define ranges
- "*" Wildcard matches all cases
- '/' Slashes define step values i.e. */5 = every 5 minutes

Example: To update a schedule to 1:30 AM, 12:30 PM and 6:30 PM, Monday-Friday

schedule-update --name schedule_name --minute 30 --hour 1,12,18 --day-of-week MON-FRI

Options:

- day-of-month The day of month for schedule. Allowed values are: 1-31,-*/ (default value: *)
- day-of-week The day of week for schedule. Allowed values are: 1-7,SUN-SAT,-*/ (default value: *)
- help Display this help and exit
- hour The hour for schedule. Allowed values are: 0-23,-*/ (default value: *)
- * --id ID to identify the schedule. Required unless "--name" is specified
- minute The minute for schedule. Allowed values are: 0-59,-*/ (default value: *)
- month The month for schedule. Allowed values are: 1-12,-*/ (default value: *)
- * --name Name to identify the schedule. Required unless "--id" is specified

snmp-clear

Usage: snmp-clear [options]

Clear SNMP configuration

Options:

- help Display this help and exit

snmp-config

Usage: snmp-config [options]

Configure SNMP service

Options:

- contact The textual identification of the contact person for this managed node, together with information on how to contact this person
- description A textual description of the entity
- dest SNMP trap destination configuration. A 3-tuple including <IP>,<version>,<community>. For example: 172.31.12.216,V2C,public
- help Display this help and exit
- location The physical location of this node

--manager SNMP manager configuration. A 3-tuple including <subnet>,<version>,<community>. For example:
 172.31.0.0/16,V2C,public
--name An administratively-assigned name for this managed node

snmp-disable

Usage: snmp-disable [options]
Disable SNMP service

Options:

--help Display this help and exit

snmp-enable

Usage: snmp-enable [options]
Enable SNMP service

Options:

--help Display this help and exit

snmp-view

Usage: snmp-view [options]
View SNMP configuration

Options:

--help Display this help and exit

software-apply

Usage: software-apply [options]
Apply software version

Options:

--all Update all nodes, mutually exclusive with "--node-name"
--help Display this help and exit
--node-name Node name, mutually exclusive with "--all"
* --version Version

software-list

Usage: software-list [options]
List software versions

Options:

--full Print extra information
--help Display this help and exit

software-package-delete

Usage: software-package-delete [options]
Delete software update packages

Options:

- help Display this help and exit
- * --package-name Package name to delete

software-update-cancel

Usage: software-update-cancel [options]
Cancel software update task

Options:

- help Display this help and exit
- * --task-id Task ID

software-update-status

Usage: software-update-status [options]
Monitor update status

Options:

- full Print extra information
- help Display this help and exit
- task-id Update task id

software-upload

Usage: software-upload [options]
Upload a software package with UPD format

Options:

- help Display this help and exit
- * --package-location The path to the UPD software package

syslog-clear

Usage: syslog-clear [options]
Clear Syslog configuration

Options:

- help Display this help and exit

syslog-config

Usage: syslog-config [options]
Configure Syslog servers

Options:

```
--help  Display this help and exit
--server Syslog server configuration. A 3-tuple including <IP>,<port>,<transport>, example:
          192.168.1.23,514,TCP. Can be used multiple times when configuring more
          than one server.
```

syslog-disable

Usage: syslog-disable [options]
Disable Syslog Event forwarding

Options:

```
--help  Display this help and exit
```

syslog-enable

Usage: syslog-enable [options]
Enable Syslog Event forwarding

Options:

```
--help  Display this help and exit
```

syslog-view

Usage: syslog-view [options]
View Syslog configuration

Options:

```
--help  Display this help and exit
```

system-shutdown

Usage: system-shutdown [options]
Use this command to perform a clean system shutdown of the Anvil system that recalls all
layouts.

Options:

```
* --force  Confirm shutdown execution
--help    Display this help and exit
--reason  Shutdown reason
```

system-view

Usage: system-view [options]
Show an overview of the system

Options:

```
--help    Display this help and exit
--summary Show only a short summary of the system
```

task-list

Usage: task-list [options]

List all running tasks in the system. The command can also be used to list completed tasks using the status filter, showing both successful and failed tasks

Options:

- ended-after List tasks that ended at or after (>=) the specified time, in the format [yyyy-MM-dd|dd-MMM-yyyy] [HH:mm:ss]
- ended-before List tasks that ended before (<) the specified time, in the format [yyyy-MM-dd|dd-MMM-yyyy] [HH:mm:ss]
- full Print extra information
- help Display this help and exit
- id The task ID
- name The task name
- started-after List tasks that started at or after (>=) the specified time, in the format [yyyy-MM-dd|dd-MMM-yyyy] [HH:mm:ss]
- started-before List tasks that started before (<) the specified time, in the format [yyyy-MM-dd|dd-MMM-yyyy] [HH:mm:ss]
- status Filter by the status of the task, possible statuses are: EXECUTING, STOPPED, FAILED, COMPLETED (successfully)

task-purge

Usage: task-purge [options]

Purge a task that FAILED or STOPPED to allow other tasks to execute that cannot currently complete

Options:

- help Display this help and exit
- id The task ID

task-resume

Usage: task-resume [options]

Resume a task that had FAILED or STOPPED

Options:

- help Display this help and exit
- id The task ID

User and Group Management

builtin-group-user-add

Usage: builtin-group-user-add [options]

Add user to a builtin group

Options:

- * --group Group name to be added to
- help Display this help and exit
- * --username The username to be added

builtin-group-user-list

Usage: builtin-group-user-list [options]

List users of a builtin group

Options:

- * --group The group name to be listed
- help Display this help and exit

builtin-group-user-remove

Usage: builtin-group-user-remove [options]

Remove user from a builtin group

Options:

- * --group Group name to be removed from
- help Display this help and exit
- * --username The username to be removed

login-policy-update

Usage: login-policy-update [options]

Update the system login policies

Options:

- allowed-networks Space separated list of allowed networks in CIDR notation (i.e. 10.50.100.0/24)
- allowed-networks-clear Allow access from all remote networks
- help Display this help and exit
- lock-after-failures The number of consecutive login failures after which an account will be locked. When not set, the account lockout feature is disabled
- lock-after-failures-clear Clears all login failure lock attributes. Resets failure counts for all users
- lock-failure-interval The time in seconds between failed login attempts that constitutes consecutive failures. When not set, the default is 15 minutes. Requires that lock-after-failures is, or has been set

--lockout-time	The amount of time in seconds an account remains locked due to too many consecutive login failures. When not set, the default is 10 minutes. Requires that lock-after-failures is, or has been set
----------------	--

login-policy-view

Usage: login-policy-view [options]
View the default login policies

Options:

--help Display this help and exit

role-create

Usage: role-create [options]
Create a user role with access permissions
Example: role-create --name graham --acl "ANY:+c+r+u+d"

Available OBJECT_TYPES include
ANY,EVENT,NODE,DATA_MOVER,NETWORK_IF,SHARE,USER,USER_GROUP,ROLE,TASK,
SMTP,NOTIFICATION_RULE,HEARTBEAT,NTP,LOGICAL_VOLUME,LDAP,CLUSTER,ELEMENTAL_OBJECTIVE,OBJECTIVE,SCHEDULE,CONDITION,SNAPSHOT_RETENTION,FILE_SNAPSHOT,OBJECT_STORAGE_VOLUME,CLOUD_MOVER,OBJECT_STORE_LOGICAL_VOLUME,SNMP,SW_UPDATE_TASK,CTDB,SHARE_SNAPSHOT,BACKUP,SAMBA_AD,DOMAIN_IDMAP,DATA_PORTAL,DNS,VOLUME_GROUP

Options:

--acl ACL, in the format: {OBJECT_TYPE}:{+{grant permissions}}{-{revoke permissions}}.
possible permissions: 'c'-create, 'r'-read, 'u'-update, 'd'-delete
--help Display this help and exit
* --name The role name

role-delete

Usage: role-delete [options]
Remove a user role

Options:

--help Display this help and exit
* --id The ID of the role to be deleted. Required unless "--name" is specified
* --name The name of the role to be deleted. Required unless "--id" is specified

role-list

Usage: role-list [options]
List user roles

Options:

--full Print extra information
--help Display this help and exit

--id The ID of the role to list
--name The name of the role to list

role-update

Usage: role-update [options]
Update an existing user role
Example: role-update --name graham --acl "ANY:+c+r+u-d"

Available OBJECT_TYPES include
ANY,EVENT,NODE,DATA_MOVER,NETWORK_IF,SHARE,USER,USER_GROUP,ROLE,TASK,
SMTP,NOTIFICATION_RULE,HEARTBEAT,NTP,LOGICAL_VOLUME,LDAP,CLUSTER,ELEME
NTAL_OBJECTIVE,OBJECTIVE,SCHEDULE,CONDITION,SNAPSHOT_RETENTION,FILE_SN
APSHOT,OBJECT_STORAGE_VOLUME,CLOUD_MOVER,OBJECT_STORE_LOGICAL_VOLU
ME,SNMP,SW_UPDATE_TASK,CTDB,SHARE_SNAPSHOT,BACKUP,SAMBA_AD,DOMAIN_ID
MAP,DATA_PORTAL,DNS,VOLUME_GROUP

Options:

- * --acl ACL, in the format: {OBJECT_TYPE}:{+{grant permissions}}|{-{revoke permissions}}.
possible permissions: 'c'-create, 'r'-read, 'u'-update, 'd'-delete
- help Display this help and exit
- * --id The ID of the role to update. Required unless "--name" is specified
- * --name The name of the role to update. Required unless "--id" is specified

user-create

Usage: user-create [options]
Create a system user

Options:

- * --email The user's email address
- first-name The user's first name
- gid Group identifier
- help Display this help and exit
- last-name The user's last name
- * --password The user's password. Passwords must be 8-20 characters long and contain at least one each of: lower case letter, upper case letter, digit and non alpha-numeric.
- public-key The user's public encryption key
- * --role-id The role ID to apply to the user (that includes the user's access permissions).
Required unless "--role-name" is specified
- * --role-name The role name to apply to the user (that includes the user's access permissions).
Required unless "--role-id" is specified
- uid User identifier
- * --username The username that will be used to identify the user in the system

user-delete

Usage: user-delete [options]
Delete a system user

Options:

```
--help  Display this help and exit
* --id   The ID of the user to delete. Required unless "--name" is specified
* --name  The name of the user to delete. Required unless "--id" is specified
```

user-import

Usage: user-import [options]

Imports users from CSV file

Example of a CSV file:

```
username,password,uid,gid,role,groups,public-key,first-name,last-name,email
user1,password1,0,0,viewer,"group1,group2",,John,Doe,john@example.com
```

Options:

```
--help  Display this help and exit
* --uri  The URI for the CSV file containing users details. For example: file:/tmp/user.csv
```

user-list

Usage: user-list [options]

List all existing users

Options:

```
--full  Print extra information
--help  Display this help and exit
--id    The ID of the user to list
--name  The name of the user to list
```

user-password-update

Usage: user-password-update [options]

Update a user password

Options:

```
--help      Display this help and exit
* --id       The ID of the user whose password will be updated. Required unless "--name" is
            specified
* --name     The name of the user whose password will be updated. Required unless "--id" is
            specified
* --new-password  The new password. Passwords must be 8-20 characters long and contain at
                  least one each of: lower case letter, upper case letter, digit and non
                  alpha-numeric.
--old-password  The user's old password
```

user-update

Usage: user-update [options]

Update the user's properties, including the applied user role. If a new role is provided it overwrites the current user's role

Options:

```
--disable    Disable the user
```

```
--email      The user's email address
--enable     Enable the user
--first-name The user's first name
--first-name-clear ""
--gid        Group identifier
--gid-clear  ""
--help       Display this help and exit
* --id       The ID that will be used to identify the user in the system. Required unless "--name" is specified
--last-name   The user's last name
--last-name-clear ""
* --name      The username that will be used to identify the user in the system. Required unless "--id" is specified
--public-key  The user's public encryption key
--public-key-clear ""
--role-id    The role ID to apply to the user (that includes the user's access permissions)
--role-name   The role name to apply to the user (that includes the user's access
              permissions)
--uid        User identifier
--uid-clear  ""
```

Data Management and Objectives

basic-objective-create

Usage: basic-objective-create [options]

Create a basic objective

Options:

--allowed-online-delay	Max time (in nano-seconds) for the file to be restored from offline Location back to online Location
--archive	Sets the archiving intent for data in a snapshot. Applicable only if selected by a Snapshot Condition. Possible values: NONE ONSITE OFFSITE.
--availability	Availability, specified as the number of nines (number between 0 and 9)
--description	The objective's description
--do-not-move	Do not move
--durability	Durability, specified as the number of nines (number between 0 and 9)
--exclude-from	Exclude from specific locations. Format: node volume object-volume volume-group:{identifier}. The identifier must be either UUID or name
--help	Display this help and exit
--max-read-response-time	Maximal read response time, in nanoseconds
--max-write-response-time	Maximal write response time, in nanoseconds
--min-read-iops	Minimum read IOPs
--min-read-throughput	Minimum read throughput, in bytes per second
--min-write-iops	Minimum write IOPS
--min-write-throughput	Minimum write throughput, in bytes per second
* --name	The objective's name
--optimize-for-capacity	Optimize for capacity
--place-on-list	Place on specific locations. Format: node volume object-volume volume-group:{identifier}. The identifier must be either UUID or name
--priority	The objective's priority. Possible values: LOW MEDIUM_LOW MEDIUM MEDIUM_HIGH HIGH.

basic-objective-delete

Usage: basic-objective-delete [options]

Delete a basic objective

Options:

--help	Display this help and exit
* --id	The ID of the objective to delete. Required unless "--name" or "--internal-id" is specified
* --internal-id	The internal ID of the objective to delete. Required unless "--id" or "--name" is specified
* --name	The name of the objective to delete. Required unless "--id" or "--internal-id" is specified

basic-objective-list

Usage: basic-objective-list [options]

List basic objective

Options:

--full	Print extra information
--help	Display this help and exit
--id	The ID of the objective to list
--internal-id	The internal ID of the objective to list
--name	The name of the objective to list

basic-objective-update

Usage: basic-objective-update [options]

Update a basic objective

Options:

--allowed-online-delay	Max time (in nano-seconds) for the file to be restored from offline Location back to online Location
--allowed-online-delay-clear	""
--archive	Sets the archiving intent for data in a snapshot. Applicable only if selected by a Snapshot Condition. Possible values: NONE ONSITE OFFSITE.
--archive-clear	""
--availability	Availability, specified as the number of nines (number between 0 and 9)
--availability-clear	""
--description	The objective's description
--description-clear	""
--do-not-move	Do not move
--durability	Durability, specified as the number of nines (number between 0 and 9)
--durability-clear	""
--exclude-from	Exclude from specific locations. Format: node volume object-volume volume-group:{identifier}. The identifier must be either UUID or name
--exclude-from-clear	""
--help	Display this help and exit
* --id	The ID of the objective to update. Required unless "--name" is specified
--internal-id	The internal ID of the objective to update. Required unless "--id" or "--name" is specified
--max-read-response-time	Maximal read response time, in nanoseconds
--max-read-response-time-clear	""
--max-write-response-time	Maximal write response time, in nanoseconds
--max-write-response-time-clear	""
--min-read-iops	Minimum read IOPs
--min-read-iops-clear	""
--min-read-throughput	Minimum read throughput, in bytes per second
--min-read-throughput-clear	""
--min-write-iops	Minimum write IOPS
--min-write-iops-clear	""
--min-write-throughput	Minimum write throughput, in bytes per second
--min-write-throughput-clear	""

* --name	The name of the objective to update. Required unless "--id" or "--internal-id" is specified
--new-name	New name.
--optimize-for-capacity	Optimize for capacity
--place-on-list	Place on specific locations. Format: node volume object-volume volume-group:{identifier}. The identifier must be either UUID or name
--place-on-list-clear	""
--priority	The objective's priority. Possible values: LOW MEDIUM_LOW MEDIUM MEDIUM_HIGH HIGH.
--priority-clear	""

condition-create

Usage: condition-create [options]
Create condition

Options:

--activity	Activity in I/Os per second (IOPS)
--help	Display this help and exit
--inactivity	Inactivity duration (e.g., 10s, 10m, 10d, 10w)
* --name	The condition name
* --pattern	The condition pattern

condition-delete

Usage: condition-delete [options]
Remove a condition. The condition must not be associated with any objective

Options:

--help	Display this help and exit
* --id	The ID of the condition to be deleted. Required unless "--name" is specified
* --name	The name of the condition to be deleted. Required unless "--id" is specified

condition-list

Usage: condition-list [options]
List conditions

Options:

--full	Print extra information
--help	Display this help and exit
--id	The ID of the condition to list
--name	The name of the condition to list
--show-auto-created	Show also the auto created conditions

condition-update

Usage: condition-update [options]
Update condition

Options:

```
--activity      Activity in I/Os per second (IOPS)
--activity-clear  ""
--help         Display this help and exit
* --id          The ID of the condition to be updated. Required unless "--name" is specified
--inactivity    Inactivity duration (e.g., 10s, 10m, 10d, 10w)
--inactivity-clear  ""
* --name        The name of the condition to be updated. Required unless "--id" is specified
--pattern       Condition pattern
```

smart-objective-create

Usage: smart-objective-create [options]
Create an objective

Options:

```
--expression   Smart objective expression
--help         Display this help and exit
* --name       The smart objective name
--rule         <comma separated conditions>:<comma separated basic objectives> (example:
               cond-1,cond-2:obj-A,obj-B)
```

smart-objective-delete

Usage: smart-objective-delete [options]
Delete an objective

Options:

```
--help         Display this help and exit
* --id          The ID of the smart objective to delete. Required unless "--name" is specified
* --name        The name of the smart objective to delete. Required unless "--id" is specified
```

smart-objective-export

Usage: smart-objective-export [options]
Export smart objectives

Options:

```
--help         Display this help and exit
--ids          The UIDs of the smart objectives to export
--names        The names of the smart objectives to export
--target       The target path to export the smart objective
```

smart-objective-import

Usage: smart-objective-import [options]
Import smart objectives from file

Options:

```
--help         Display this help and exit
--insecure     Connect with trust all certificate in case of https
```

--merge Merge with existing or fail in case of collision
--names The names of the smart objectives to import
--prefix The prefix to be added to the names of the imported objectives
* --source The path of the file listing the smart objective to import

smart-objective-list

Usage: smart-objective-list [options]
List objectives

Options:

--full Print extra information
--help Display this help and exit
--id The ID of the smart objective to list
--internal-id The internal ID of the smart objective to list
--name The name of the smart objective to list

smart-objective-update

Usage: smart-objective-update [options]
Update an objective

Options:

--expression Smart objective expression
--help Display this help and exit
* --id The ID of the smart objective to update. Required unless "--name" is specified
* --name The name of the smart objective to update. Required unless "--id" is specified
--new-name New name.
--rule <comma separated conditions>:<comma separated basic objectives> (example:
cond-1,cond-2:obj-A,obj-B,obj-C)

Storage and Volumes

drive-list

Usage: drive-list [options]

List disk drives

Options:

- full Print extra information
- help Display this help and exit
- id The ID of the disk drive to list
- node-name The node name

logical-volume-create

Usage: logical-volume-create [options]

Create logical volume

Options:

- device-path The physical device path
- force Force creation will reformat existing volume
- help Display this help and exit
- node-name The node name

logical-volume-delete

Usage: logical-volume-delete [options]

Delete logical volume

Options:

- help Display this help and exit
- * --id The logical volume ID

logical-volume-discover

Usage: logical-volume-discover [options]

Discover information about logical volume

Options:

- help Display this help and exit
- * --id The logical volume ID

logical-volume-list

Usage: logical-volume-list [options]

List logical volumes

Options:

- full Print extra information
- help Display this help and exit
- id The ID of the logical volume to list

--node-name The node name

node-add

Usage: node-add [options]
Create a node in the system

Options:

- additional-info Additional value. Format: key=value
- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- cert The node's authentication certificate. This option is mandatory for third-party nodes, and is mutually exclusive of a username/password)
- help Display this help and exit
- ip Node IP address. This option is mandatory for third-party nodes
- * --name The name to assign to the node
- password Authentication password. This option is mandatory for third-party nodes. The cert option must accompany this option
- * --type Node type. Possible values: PD | NETAPP_CMODE | NETAPP_7MODE | NETAPP_CLOUD | EMC_ISILON | EMC_VNX | EMC_UNITY | GOOGLE_CLOUD_FILESTORE | SOFTNAS_CLOUD | OTHER.
- username Authentication username This option is mandatory for third-party nodes. The cert option must accompany this option

node-list

Usage: node-list [options]
List all nodes in the system

Options:

- full Print extra information
- help Display this help and exit
- id The ID of the node to list
- name The name of the node to list
- unauthorized List only discovered unauthorized nodes connected to the system

node-mode-change

Usage: node-mode-change [options]
Modify node's mode

Options:

- help Display this help and exit
- * --id Node ID. Required unless "--name" or "--internal-id" is specified
- * --internal-id Node internal ID. Required unless "--id" or "--name" is specified
- * --mode Target mode. Possible values: ONLINE | MAINTENANCE | POWEROFF | REBOOT.
- * --name Node name. Required unless "--id" or "--internal-id" is specified

node-refresh

Usage: node-refresh [options]
Refresh a node in the system

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- help Display this help and exit
- * --id Node ID. Required unless "--name" is specified
- * --name Node name. Required unless "--id" or "--internal-id" is specified
- rescan Rescan disk drives in node

node-remove

Usage: node-remove [options]
Remove a node from the system. A node that contains system services cannot be removed

Options:

- async Causes the command to be executed asynchronously. A reference task identifier will be returned
- force Force remove, even if the node is down
- help Display this help and exit
- * --id The ID of the node to remove. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the node to remove. Required unless "--id" or "--name" is specified
- * --name The name of the node to remove. Required unless "--id" or "--internal-id" is specified

node-storage-repair

Usage: node-storage-repair [options]
Repair node storage volumes

Options:

- help Display this help and exit
- * --id Node ID to be repaired. Required unless "--name" is specified
- * --name Node name to be repaired. Required unless "--id" is specified

node-update

Usage: node-update [options]
Update a node in the system

Options:

- cert The node's authentication certificate
- help Display this help and exit
- * --id Node ID. Required unless "--name" is specified
- ip Node IP address
- * --internal-id Node internal ID. Required unless "--id" or "--name" is specified
- * --name Node name. Required unless "--id" is specified
- password Authentication password

--username Authentication username

object-storage-add

Usage: object-storage-add [options]
Add an object storage node to the product

Options:

* --access-key	Object storage access key
--allow-self-signed-certificate	Trust the server's certificate without checking its CA chain
--async	Causes the command to be executed asynchronously. A reference task identifier will be returned
--bucket-naming-virtual-host	Bucket names are prefixed to the hostname (mybucket.myhost.org)
--endpoint	* Object storage endpoint. Required unless --type specifies AMAZON_S3, AZURE, or GOOGLE_CLOUD
--help	Display this help and exit
* --name	The name to assign to the object storage
--proxy-host	Proxy host name/IP
--proxy-password	Proxy password
--proxy-port	Proxy port
--proxy-username	Proxy username
* --secret-key	Object storage secret key
--type	Object storage type. Possible values: AMAZON_S3 ACTIVE_SCALE_S3 IBM_S3 CLOUDIAN_S3 ECS_S3 GENERIC_S3 GOOGLE_S3 SCALITY_S3 STORAGE_GRID_S3 AZURE GOOGLE_CLOUD HCP_S3.

object-storage-update

Usage: object-storage-update [options]
Update an object storage node

Options:

--access-key	Object storage access key
--allow-self-signed-certificate	Trust the server's certificate without checking its CA chain
--bucket-naming-path-style	Bucket names are suffixed as a path (myhost.org/mybucket)
--bucket-naming-virtual-host	Bucket names are prefixed to the hostname (mybucket.myhost.org)
--disallow-self-signed-certificate	Validate the server certificate's CA chain
--endpoint	* Object storage endpoint. Required unless --type specifies AMAZON_S3, AZURE, or GOOGLE_CLOUD
--endpoint-clear	Reset the endpoint to its default
--help	Display this help and exit
* --id	The ID of the object storage to update. Required unless "--name" or "--internal-id" is specified
* --internal-id	The internal ID of the object storage to update. Required unless "--id" or "--name" is specified

* --name	The name of the object storage to update. Required unless "--id" or "--internal-id" is specified
--proxy-clear	Remove the proxy definitions, i.e. don't use proxy for this Object storage
--proxy-host	Proxy host name/IP
--proxy-password	Proxy password
--proxy-port	Proxy port
--proxy-username	Proxy username
--secret-key	Object storage secret key
--type	Object storage type. Possible values: AMAZON_S3 ACTIVE_SCALE_S3 IBM_S3 CLOUDIAN_S3 ECS_S3 GENERIC_S3 GOOGLE_S3 SCALITY_S3 STORAGE_GRID_S3 AZURE GOOGLE_CLOUD HCP_S3.

object-volume-add

Usage: object-volume-add [options]
Add an object storage volume to the product

Options:

--access-key	Access key, if not provided, the object storage credentials will be used
--availability	Volume availability capability, specified as the number of nines (number between 1 and 11)
--durability	Volume durability capability, specified as the number of nines (number between 1 and 11)
--help	Display this help and exit
* --logical-volume-id	object logical volume ID. Required unless "--logical-volume-name" is specified
* --logical-volume-name	object logical volume. Required unless "--logical-volume-id" is specified
--name	The object storage volume name. If not provided, a default name will be assigned
* --node-id	The node ID. Required unless "--node-name" is specified
* --node-name	The node name. Required unless "--node-id" is specified
--online-delay	Max time (in nano-seconds) for the file to be restored
--secret-key	Secret key, if not provided, the object storage credentials will be used
--shared	Allows an object storage volume already reserved by another Anvil to be added

object-volume-decommission

Usage: object-volume-decommission [options]
Start the object storage volume decommission process

Options:

--help	Display this help and exit
* --id	Object Storage Volume ID. Required unless "--name" or "--internal-id" is specified
* --internal-id	Object Storage Volume internal ID. Required unless "--id" or "--name" is specified

* --name Object Storage Volume name. Required unless "--id" or "--internal-id" is specified
--replace-with List of locations to replace the decommissioned volume. Example:
node:<name>,volume-group:<name>,volume:<name>,object-volume:<name>

object-volume-decommission-cancel

Usage: object-volume-decommission-cancel [options]
Cancel the object storage volume decommission process

Options:
--help Display this help and exit
* --id Object Storage Volume identifier. Required unless "--name" or "--internal-id" is specified
* --internal-id Object Storage Volume internal ID. Required unless "--id" or "--name" is specified
* --name Object Storage Volume name. Required unless "--id" or "--internal-id" is specified

object-volume-fail

Usage: object-volume-fail [options]
Fail the object storage volume

Options:
--help Display this help and exit
* --id The ID of the object storage volume to fail. Required unless "--name" or "--internal-id" is specified
* --internal-id The internal ID of the object storage volume to fail. Required unless "--id" or "--name" is specified
* --name The name of the object storage volume to fail. Required unless "--id" or "--internal-id" is specified

object-volume-list

Usage: object-volume-list [options]
List object storage volumes

Options:
--full Print extra information
--help Display this help and exit
--id The ID of the volume to list
--internal-id The internal ID of the volume to list
--name The name of the volume to list

object-volume-remove

Usage: object-volume-remove [options]
Remove an object storage volume from the system. The object storage volume must be in the DECOMMISSIONED or FAILED state

Options:

```
--help      Display this help and exit
* --id       The ID of the object storage volume to remove. Required unless "--name" or "--internal-id" is specified
* --internal-id The internal ID of the object storage volume to remove. Required unless "--id" or "--name" is specified
* --name      The name of the object storage volume to remove. Required unless "--id" or "--internal-id" is specified
```

object-volume-set-available

Usage: object-volume-set-available [options]
Mark an unavailable object storage volume as available

Options:

```
--help      Display this help and exit
* --id       The ID of the object storage volume to mark
            available. Required unless "--name" or "--internal-id" is specified
* --internal-id The internal ID of the object storage volume to mark available. Required unless "--id" or "--name" is specified
* --name      The name of the object storage volume to mark available. Required unless "--id" or "--internal-id" is specified
```

object-volume-set-unavailable

Usage: object-volume-set-unavailable [options]
Mark an object storage volume as unavailable

Options:

```
--help      Display this help and exit
* --id       The ID of the object storage volume to mark unavailable. Required unless "--name"
            or "--internal-id" is specified
* --internal-id The internal ID of the object storage volume to mark unavailable. Required
            unless "--id" or "--name" is specified
* --name      The name of the object storage volume to mark unavailable. Required unless "--id"
            or "--internal-id" is specified
```

object-volume-update

Usage: object-volume-update [options]
Update object storage volume

Options:

```
* --access-key Access key
--availability Volume availability capability, specified as the number of nines (number between
               1 and 11)
--durability   Volume durability capability, specified as the number of nines (number between 1
               and 11)
--help         Display this help and exit
```

```
* --id          object storage volume ID. Required unless "--name" or "--internal-id" is specified
* --internal-id object storage volume internal ID. Required unless "--id" or "--name" is specified
* --name        object storage volume name. Required unless "--id" or "--internal-id" is specified
--new-name     object storage new name
--online-delay Max time (in nano-seconds) for the file to be restored
* --secret-key Secret key
```

volume-add

Usage: volume-add [options]

Add a storage volume to the product

Options:

--access-type	The access type of the storage volume Possible values: READ_ONLY READ_WRITE.
--assimilation	Assimilate data from the volume
--async	Causes the command to be executed asynchronously. A reference task identifier will be returned
--availability	The storage volume availability capability, specified as the number of nines (number between 1 and 11)
--cost	Estimated cost of the storage volume
--destination-path	The path within the share to assimilate to
--durability	The storage volume durability capability, specified as the number of nines (number between 1 and 11)
--force	Delete a previous installation's data from the volume
--help	Display this help and exit
--log-assimilation	Causes assimilation to log data into <share/mount/path>/assimilation-logs-<date>/
* --logical-volume-id	The logical volume ID. Required unless "--logical-volume-name" is specified
* --logical-volume-name	The logical volume name. Required unless "--logical-volume-id" is specified
--name	The storage volume name. If not provided, default name will be assigned
* --node-id	The node ID. Required unless "--node-name" is specified
* --node-name	The node name. Required unless "--node-id" is specified
--path	The path within the share to assimilate to
--restart-assimilation	Forces assimilation to restart (where an assimilation of the same data into the same share already exists)
--share-id	The share ID to assimilate data to
--share-name	The share name to assimilate data to
--smb-default-group	An Active Directory group to use for SID mapping if a group SID does not have a mapping (because the group has been deleted). Valid forms are <name>@<domain> and <domain>\<name>
--smb-default-user	An Active Directory user to use for SID mapping if a user SID does not have a mapping (because the account has been deleted). Valid forms are <name>@<domain> and <domain>\<name>
--smb-drop-unmapped-ace	Specifies that when assimilating SMB attributes, Windows access control entries with unmapped users or groups will be dropped.
--smb-password	Password for SMB username used to assimilate SMB data
--smb-server	Fully-qualified domain name of the SMB server from which data is being assimilated

--smb-share	SMB share name from which data is being assimilated
--smb-username	SMB username used to assimilate SMB data. Valid forms are <name>@<domain> and <domain>\<name>
--source-path	The path within the volume to assimilate from
--utilization-threshold	The storage volume utilization threshold

volume-assimilation

Usage: volume-assimilation [options]
Assimilate an existing storage volume

Options:

--async	Causes the command to be executed asynchronously. A reference task identifier will be returned
--destination-path	The path within the share to assimilate to
--help	Display this help and exit
* --id	The volume ID. Required unless "--name" or "--internal-id" is specified
* --internal-id	The internal ID of the volume. Required unless "--id" or "--name" is specified
* --name	The volume name. Required unless "--id" or "--internal-id" is specified
--path	The path within the share to assimilate to
* --share-id	The share ID to assimilate data to. Required unless "--share-name" is specified
* --share-name	The share name to assimilate data to. Required unless "--share-id" is specified
--smb-default-group	An Active Directory group to use for SID mapping if a group SID does not have a mapping (because the group has been deleted). Valid forms are <name>@<domain> and <domain>\<name>
--smb-default-user	An Active Directory user to use for SID mapping if a user SID does not have a mapping (because the account has been deleted). Valid forms are <name>@<domain> and <domain>\<name>
--smb-drop-unmapped-ace	Specifies that when assimilating SMB attributes, Windows access control entries with unmapped users or groups will be dropped.
--smb-password	Password for SMB username used to assimilate SMB data
--smb-server	Fully-qualified domain name of the SMB server from which data is being assimilated
--smb-share	SMB share name from which data is being assimilated
--smb-username	SMB username used to assimilate SMB data. Valid forms are <name>@<domain> and <domain>\<name>
--source-path	The path within the volume to assimilate from

volume-decommission

Usage: volume-decommission [options]
Start the storage volume decommission process

Options:

--help	Display this help and exit
* --id	Storage Volume identifier. Required unless "--name" or "--internal-id" is specified
* --internal-id	Storage Volume internal identifier. Required unless "--id" or "--name" is specified
* --name	Storage Volume name. Required unless "--id" or "--internal-id" is specified

--replace-with List of locations to replace the decommissioned volume. Example:
node:<name>,volume-group:<name>,volume:<name>,object-volume:<name>

volume-decommission-cancel

Usage: volume-decommission-cancel [options]
Cancel the storage volume decommission process

Options:

- help Display this help and exit
- * --id Storage Volume identifier. Required unless "--name" or "--internal-id" is specified
- * --internal-id Storage Volume internal identifier. Required unless "--id" or "--name" is specified
- * --name Storage Volume name. Required unless "--id" or "--internal-id" is specified

volume-fail

Usage: volume-fail [options]
Fail the storage volume

Options:

- help Display this help and exit
- * --id The ID of the storage volume to fail. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the storage volume to fail. Required unless "--id" or "--name" is specified
- * --name The name of the storage volume to fail. Required unless "--id" or "--internal-id" is specified

volume-group-create

Usage: volume-group-create [options]
Create a new volume group

Options:

- description The volume group's description
- expressions The volume group expression(s). Expressions are separated by '&'
- help Display this help and exit
- * --name The volume group name

volume-group-delete

Usage: volume-group-delete [options]
Delete a volume group

Options:

- help Display this help and exit
- * --id The ID of the volume group to delete. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the volume group to delete. Required unless "--id" or "--name" is specified

* --name The name of the volume group to delete. Required unless "--id" or "--internal-id" is specified

volume-group-list

Usage: volume-group-list [options]

Display a detailed list of all volume groups available in the system

Options:

- full Print extra information
- help Display this help and exit
- id The ID of the volume group to list
- internal-id The internal ID of the volume group to list
- name The name of the volume group to list

volume-group-update

Usage: volume-group-update [options]

Update a volume group

Options:

- description The volume group's description
- description-clear ""
- expressions The volume group expression(s). Expressions are separated by '&'
- expressions-clear ""
- help Display this help and exit
- * --id The ID of the volume group to update. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the volume group to update. Required unless "--id" or "--name" is specified
- * --name The name of the volume group to update. Required unless "--id" or "--internal-id" is specified
- new-name The volume group updated name

volume-list

Usage: volume-list [options]

Display a detailed list of all storage volumes available in the system. Two types of lists can be displayed: a detailed list and a Summary list (default)

Options:

- full Print extra information
- help Display this help and exit
- id The ID of the storage volume to list
- internal-id The internal ID of the volume to list
- name The name of the storage volume to list

volume-remove

Usage: volume-remove [options]

Remove a storage volume from the system. The storage volume must be in the DECOMMISSIONED or FAILED state

Options:

- help Display this help and exit
- * --id The ID of the storage volume to remove. Required unless "--name" or "--internal-id" is specified
- * --internal-id The internal ID of the storage volume to remove. Required unless "--id" or "--name" is specified
- * --name The name of the storage volume to remove. Required unless "--id" or "--internal-id" is specified

volume-update

Usage: volume-update [options]

Update storage volume attributes, including the volume performance and availability attributes

Options:

- | | |
|---------------------------|--|
| --availability | The storage volume availability capability, specified as the number of nines (number between 1 and 11) |
| --clone | The storage volume clone capability |
| --durability | The storage volume durability capability, specified as the number of nines (number between 1 and 11) |
| --encryption | The storage volume encryption capability |
| --help | Display this help and exit |
| * --id | The ID of the storage volume to update. Required unless "--name" or "--internal-id" is specified |
| * --internal-id | The internal ID of the storage volume to update. Required unless "--id" or "--name" is specified |
| * --name | The name of the storage volume to update. Required unless "--id" or "--internal-id" is specified |
| --new-name | The storage volume new name |
| --read-bandwidth | The storage volume read bandwidth (in kb/sec) |
| --read-iops | The storage volume read number of IOPs |
| --read-latency | The storage volume read latency (in microsecs) |
| --snapshot | The storage volume snapshot capability |
| --tolerable-read-latency | The storage volume tolerable read latency (in nanoseconds) |
| --tolerable-write-latency | The storage volume tolerable write latency (in nanoseconds) |
| --utilization-threshold | The storage volume utilization threshold |
| --write-bandwidth | The storage volume write bandwidth (in kb/sec) |
| --write-iops | The storage volume write number of IOPs |
| --write-latency | The storage volume write latency (in microsecs) |

Snapshots and Cloning

file-snapshot-create

Usage: file-snapshot-create [options]

Create file snapshot

Example: file-snapshot-create --filename /test/VM2/*.vmdk --now

Options:

- * --filename Source file path. The filename in the path may include wild-card characters (for example, /share/dir/file*.txt)
- help Display this help and exit
- now Create immediate snapshot of the file
- retention-name The name of the retention policy
- schedule-name The name of the schedule policy

file-snapshot-delete

Usage: file-snapshot-delete [options]

Delete file snapshots

Options:

- all Deletes all existing snapshots
- * --filename Source file path. The filename in the path may include wild-card characters (for example: /share/dir/file*.txt)
- help Display this help and exit
- time Date-time expression in format yyyy-MM-ddThh-mm-ss. The expression may contain wild-card characters (for example: 2000-01-30*)

file-snapshot-list

Usage: file-snapshot-list [options]

List file snapshots

Options:

- * --filename Source file path. The filename in the path may include wild-card characters (for example: /share/dir/file*.txt)
- help Display this help and exit

file-snapshot-restore

Usage: file-snapshot-restore [options]

Restore files from snapshots

Options:

- * --filename Source file path. The filename in the path may include wild-card characters (for example: /share/dir/file*.txt)
- help Display this help and exit
- * --time Date-time expression in format yyyy-MM-ddThh-mm-ss. The expression may contain wild-card characters (for example: 2000-01-30*)

file-snapshot-schedule-list

Usage: file-snapshot-schedule-list [options]
List scheduled file snapshots

Options:

- filename Source file path. The filename in the path may include wild-card characters (for example: /share/dir/file*.txt)
- help Display this help and exit
- id The ID of the file snapshot schedule to list

file-snapshot-update

Usage: file-snapshot-update [options]
Update file snapshot schedule

Options:

- * --filename Source file path. The filename in the path may include wild-card characters (for example: /share/dir/file*.txt)
- help Display this help and exit
- remove-retention Remove the retention policy from file snapshots
- remove-schedule Remove both schedule and retention from file snapshots
- retention-name The name of the retention policy
- schedule-name The name of the schedule policy

snapshot-retention-create

Usage: snapshot-retention-create [options]
Create a snapshot retention policy

Options:

- help Display this help and exit
- * --name The name of the snapshot retention policy
- number-of-copies The number of copies the policy should create
- retention-time The time interval to retain snapshots, from the time of the last snapshot, in the format: dd:HH:mm

snapshot-retention-delete

Usage: snapshot-retention-delete [options]
Delete snapshot retention policy

Options:

- help Display this help and exit
- * --id The ID of the snapshot policy to delete. Required unless "--name" is specified
- * --name The name of the snapshot policy to delete. Required unless "--id" is specified

snapshot-retention-list

Usage: snapshot-retention-list [options]
List snapshot retention policies

Options:

- full Print extra information
- help Display this help and exit
- id The ID of the snapshot retention policy to list
- name The name of the snapshot retention policy to list

snapshot-retention-update

Usage: snapshot-retention-update [options]

Update snapshot retention policy

Options:

- help Display this help and exit
- * --id The name of the snapshot retention policy to list. Required unless "--name" is specified
- * --name The ID of the snapshot retention policy to list. Required unless "--id" is specified
- number-of-copies The number of copies the policy should create
- retention-time The time interval to retain snapshots, from the time of the last snapshot, in the format: dd:HH:mm

Networking

floating-ip-add

Usage: floating-ip-add [options]
Add new floating IP address (cluster or portal)

Options:

- cluster Add cluster floating IP address
- help Display this help and exit
- * --ip Floating IP address to add
- portal Add portal floating IP address

floating-ip-remove

Usage: floating-ip-remove [options]
Remove existing floating IP address (cluster or portal)

Options:

- cluster Remove cluster floating IP address
- help Display this help and exit
- * --ip Floating IP address to remove
- portal Remove portal floating IP address

gateway-update

Usage: gateway-update [options]
Update gateway configuration

Options:

- help Display this help and exit
- ipv4 Set the gateway IPv4 address
- ipv4-clear Clear the gateway IPv4 address
- ipv6 Set the gateway IPv6 address
- ipv6-clear Clear the gateway IPv6 address
- node-name The node name

gateway-view

Usage: gateway-view [options]
List gateway configuration

Options:

- help Display this help and exit
- node-name The node name

interface-create

Usage: interface-create [options]
Create virtual network interface

Options:

- help Display this help and exit
- interface-id The physical network interface ID
- interface-name The physical network interface name
- ip Set the network interface IP address
- mtu Set the network interface mtu
- node-name The node name
- roles Set the network interface role(s) Possible values: mgmt | data | ha | portal.
- * --vlan-id Set the network interface vlan ID

interface-delete

Usage: `interface-delete [options]`
Delete virtual network interface

Options:

- help Display this help and exit
- interface-id The virtual network interface ID
- interface-name The virtual network interface name
- node-name The node name

interface-list

Usage: `interface-list [options]`
List network interfaces

Options:

- full Print extra information
- help Display this help and exit
- interface-id The ID of the network interface to list
- node-name The node name

interface-update

Usage: `interface-update [options]`
Update physical/virtual network interface

Options:

- help Display this help and exit
- interface-id The network interface ID
- interface-name The network interface name
- ip Set the network interface IP address
- ip-clear Remove the network interface IP address
- mtu Set the network interface mtu
- node-name The node name
- roles Set the network interface role(s) Possible values: mgmt | data | ha | portal.
- roles-clear Clear the network interface role(s)
- vlan-id Set the network interface vlan ID (may change the interface name)

static-route-add

Usage: static-route-add [options]

Add a new static route

Options:

- * --destination The static route destination IP address (CIDR notation optional)
- help Display this help and exit
- * --next-hop The IP address of the next hop

static-route-delete

Usage: static-route-delete [options]

Delete a static route

Options:

- * --destination The destination IP address of the route to be deleted
- help Display this help and exit
- * --next-hop The next hop IP address of the route to be deleted

static-route-list

Usage: static-route-list [options]

List static routes

Options:

- help Display this help and exit

subnet-gateway-add

Usage: subnet-gateway-add [options]

Add a new subnet gateway

Options:

- * --gateway The IP address of the subnet gateway
- help Display this help and exit
- * --subnet The subnet IP address in CIDR notation

subnet-gateway-delete

Usage: subnet-gateway-delete [options]

Delete a subnet gateway

Options:

- help Display this help and exit
- * --subnet The subnet IP address in CIDR notation

subnet-gateway-list

Usage: subnet-gateway-list [options]

List subnet gateways



Options:

--help Display this help and exit

Technology Preview

local-site-update

Usage: local-site-update [options]
Update the local site

Options:

- help Display this help and exit
- name The new name of the local site

local-site-view

Usage: local-site-view [options]
View the local site

Options:

- help Display this help and exit

Alphabetical Command Index

ad-discover
ad-join
ad-leave
ad-view
backup-create
backup-restore
backup-schedule-list
backup-update
basic-objective-create
basic-objective-delete
basic-objective-list
basic-objective-update
builtin-group-user-add
builtin-group-user-list
builtin-group-user-remove
cluster-update
cluster-view
condition-create
condition-delete
condition-list
condition-update
dns-list
dns-update
domain-idmap-add
domain-idmap-delete
domain-idmap-list
domain-idmap-reload
dp-update
drive-list
event-list
event-smtpgw-define
event-smtpgw-list
file-snapshot-create
file-snapshot-delete
file-snapshot-list
file-snapshot-restore
file-snapshot-schedule-list
file-snapshot-update
floating-ip-add
floating-ip-remove
gateway-update
gateway-view
ha-node-add
ha-node-decommission
heartbeat-send
heartbeat-update
heartbeat-view
interface-create
interface-delete
interface-list
interface-update

ldap-clear
ldap-list
ldap-update
license-activate
license-deactivate
license-request-export
local-site-update
local-site-view
logical-volume-create
logical-volume-delete
logical-volume-discover
logical-volume-list
login-policy-update
login-policy-view
metric-list
nis-config
nis-view
node-add
node-list
node-mode-change
node-refresh
node-remove
node-storage-repair
node-update
notification-rule-create
notification-rule-list
notification-rule-remove
notification-rule-update
ntp-list
ntp-update
object-storage-add
object-storage-update
object-volume-add
object-volume-decommission
object-volume-decommission-cancel
object-volume-fail
object-volume-list
object-volume-remove
object-volume-set-available
object-volume-set-unavailable
object-volume-update
proxy-clear
proxy-set
remote-site-list
remote-site-remove
role-create
role-delete
role-list
role-update
schedule-create
schedule-delete
schedule-list
schedule-update

```
share-clone-create
share-create
share-delete
share-list
share-mount
share-move
share-objective-add
share-objective-remove
share-offline
share-online
share-snapshot-create
share-snapshot-delete
share-snapshot-list
share-snapshot-restore
share-snapshot-schedule-list
share-snapshot-update
share-undelete
share-unmount
share-update
smart-objective-create
smart-objective-delete
smart-objective-export
smart-objective-import
smart-objective-list
smart-objective-update
smb-config
snapshot-retention-create
snapshot-retention-delete
snapshot-retention-list
snapshot-retention-update
snmp-clear
snmp-config
snmp-disable
snmp-enable
snmp-view
software-apply
software-list
software-package-delete
software-update-cancel
software-update-status
software-upload
static-route-add
static-route-delete
static-route-list
subnet-gateway-add
subnet-gateway-delete
subnet-gateway-list
support-bundle
syslog-clear
syslog-config
syslog-disable
syslog-enable
syslog-view
```

```
system-shutdown
task-list
task-purge
task-resume
user-create
user-delete
user-import
user-list
user-password-update
user-update
volume-add
volume-assimilation
volume-decommission
volume-decommission-cancel
volume-fail
volume-group-create
volume-group-delete
volume-group-list
volume-group-update
volume-list
volume-remove
volume-update
```